



•rayNET



**RayVentory**

Smarter Software and Hardware Inventory

Quick Guide RayVentory - Port Binding Http(s)

Date: 21.05.2015

**Firma**

Straße  
PLZ Ort


**Raynet GmbH**

Technologiepark 20  
33100 Paderborn

RayVentory is part of RaySuite.

# Quick Guide RayVentory - Port Binding Http(s)

This guide is designed to reconfigure your RayVentory server for a custom port binding. It will cover all necessary changes for the RayVentory server and its services.



## Before you proceed


This guide assumes:

- The RayVentory server is already setup and preconfigured.
- You want to reconfigure web based services and protocols, e.g. http and https.
- You are familiar with the Internet Information Services (IIS) Manager.
- You have a basic understanding for the RayVentory server and portal.

The RayVentory release notes and full-size documentation are available in addition to this document.


## I. Internet Information Services (IIS) Manager

To change the port bindings for a web protocol, select them from the Default Web Site context menu:



## Add a new binding

To add a new binding, select the desired protocol and port. E.g. Port 81 for http:




Command line parameter:

```
%SYSTEMROOT%\System32\inetsrv\appcmd.exe set config /section:system.applicationHost/sites
/+"[name='Default Web Site'].bindings.[protocol='http',bindingInformation='*:81:']"
/commit:apphost
```

## Remove an existing binding

To clear a binding, select and remove an entry from your list. E.g. Port 80 for http:



Command line parameter:

```
%SYSTEMROOT%\System32\inetsrv\appcmd.exe set config /section:system.applicationHost/sites
/-"[name='Default Web Site'].bindings.[protocol='http',bindingInformation='*:80:']"
/commit:apphost
```

## Test the new binding


Start a local browser and type in <servername>:<newport>, e.g. <http://rayven10:81/> :



The IIS default website is shown.

## II. RayVentory Portal

Start the RayVentory Admin UI and change the protocol and port for the PORTAL URL setting:




### III. RayManageSoft

Before modifying the RMS settings keep the following in mind:


There is only one protocol and port for each connection type. Nevertheless it is possible to have multiple connection types for each server. E.g. multiples download locations for the core server.

To change your settings, start the RayManageSoft console and select the infrastructure tile on your dashboard.




#### Change the distribution location port

Edit the distribution server in the infrastructure *overview*. Change the port for the distribution between servers or local the replication. E.g. the Core Distribution Server:



## Change the download location port

Edit the download location in the *distribution* tab. Change the port for download location [general] and the file push [distribution settings]:




The screenshot shows the RayManageSoft Infrastructure interface. The 'distribution' tab is selected. A table lists distribution locations, with the first entry highlighted: 192.168.104.31, Core Distribution Server, http://192.168.104.31:80/ManagementSoftware/.

Two configuration windows are shown side-by-side for the selected location:

- General Configuration:** Shows the 'Protocol' set to HTTP and the 'Port' set to 81.
- Distribution Settings Configuration:** Shows the 'Protocol' set to HTTP and the 'Port' set to 81.

## Change the reporting location port

Edit the reporting location in the *reporting* tab. Change the feedback channel port for all attached servers and devices:




The screenshot shows the RayManageSoft Infrastructure interface. The 'reporting' tab is selected. A table lists reporting locations, with the first entry highlighted: 192.168.104.31, Core Distribution Server, http://192.168.104.31:80/ManagementSoftware/.

A configuration window is shown for the selected location:

- Reporting Configuration:** Shows the 'Protocol' set to HTTP and the 'Port' set to 81.

## Update failover locations

Distribute your changes to entire distribution hierarchy. Run the *update failover locations* wizard from the *maintenance tab*:



The screenshot shows the RayManage Infrastructure interface. The top navigation bar includes a back arrow, the word "Infrastructure", and the RayManage logo. Below this is a blue bar with a home icon and the text "GET STARTED". A left sidebar lists navigation options: Dashboard, Get started, Devices, Infrastructure (highlighted), Tasks, Scheduling, Reports, and Reporting. The main content area has a breadcrumb trail: "overview | distribution | reporting | groups | maintenance" (with "maintenance" highlighted in a red box). Below the breadcrumb are four action items: "Verify distribution configuration" (green icon), "Update failover locations" (blue icon, highlighted with a red box), and "Distribution settings" (purple icon).

## Change default settings

Set the new port as default settings in the *Distribution settings* in the *maintenance tab*:

